

Fire Regime and Condition Class (FRCC) Installation Notes

If you have previously installed the FRCC Standard Landscape Software, go to the Upgrade Notes below.

1. The FRCC Standard Landscape software has been developed as a Microsoft Access application. Make sure that MS Access 2000 (or a later version of Access) has been installed on the PC the software will be installed on.
2. Download the FRCC Standard Landscape software file from the FRCC website. The FRCC software file is a zip file whose name starts with FRCCstd_install. It can be downloaded from www.frcc.gov by clicking on the “Software” menu, then selecting the “FRCC S/W Installation” menu item.
3. Extract FRCCapp.mde and FRCCdata.mdb from installation file into a folder on the destination computer. (If the files are being copied from a CD, make sure they are not Read-Only.)
4. Run FRCCapp.mde. The application will ask the user to verify the path where FRCCdata.mdb resides. The default assumes that FRCCdata.mdb was placed in the same folder as FRCCapp.mde. The user will only be queried for this path the first time the application is run.
5. The FRCC menu will appear, click the “Enter/View Data” button to enter the FRCC Data Entry/Viewing form.

Upgrade Notes – upgrading from a version prior to 1.0.5:

If you have previously installed a version of the FRCC Standard Landscape software prior to 1.0.5, it can be upgraded to the current version with the following steps:

1. Extract FRCCapp.mde from the installation zip file into the folder on the destination computer where the previous version of the software was installed. This will copy FRCCapp.mde over the previous version of that file. The FRCC software file is a zip file whose name starts with FRCCstd_install. It can be downloaded from www.frcc.gov by clicking on the “Software” menu, then selecting the “FRCC S/W Installation” menu item.
2. Extract FRCCdata.mdb into a temporary folder. (e.g. c:\temp). Do not overwrite the existing copy of FRCCdata.mdb that was installed previously.
3. Run FRCCapp.mde. The application will ask the user to verify the path where FRCCdata.mdb resides. The default assumes that FRCCdata.mdb was placed in the same folder as FRCCapp.mde. Make sure you specify the path where the previous version of the FRCCdata.mdb resides which contains your data. The user will only be queried for this path the first time the application is run.
4. The FRCCapp.mde will detect that you are upgrading the software and will ask you where to find the new version of FRCCdata.mdb. (e.g. c:\temp).
5. FRCCapp.mde will complete the rest of the upgrade process automatically.